

Electric Potential
&
Electric Potential Energy

The force on a test charge q_0 in an \mathbf{E} -field:

$$\vec{F}_{q_0, field} = q_0 \vec{E}$$

To move a charge around in an electric field, **work** is by the field (and by an external agent).

$$W_{field} = -W_{ext. agent}$$

Recall:
$$dW_{field} = \vec{F}_{q_0, field} \cdot d\vec{s}$$


So...
$$W_{field} = q_0 \int_A^B \vec{E} \cdot d\vec{s} = -\Delta U$$

where $d\vec{s}$ is a differential displacement along some path from Point A to Point B .

Since \mathbf{F}_{field} is a **conservative force**, what does this imply about how ΔU depends on the path taken from Point A to Point B ?

No path dependence!

A mechanical analogy may be helpful...



Because “opposites” attract and “likes” repel, assemblies of charge possess (electric) potential energy.


We’ll see that like *universal gravitation*, it is often convenient to **define $U = 0$** when the charges are **∞ apart**.

Defining *Potential*

Again, consider a mechanical analogy: **Gravitational Potential**

We can define gravitational potential, “*GP*”, as the “gravitational potential energy per unit mass.”

That is, $GP = \frac{U_g}{m} = \frac{mgh}{m} = gh$



Note that *GP* depends only on location in space. There is no gravitational potential *energy* until a mass *m* is placed at a location where the gravitational potential is nonzero.

Twice the mass, then twice the U_g and **twice the work** to move it.

Ten times the mass, then ten times the U_g and **ten times the work**.

Defining *Electric Potential*

Similarly, moving a particle with **twice the charge** in an electric field requires **twice as much work**.

Moving a particle with **ten times the charge** means **ten times the work**.

We define **Electric Potential, V** , as the
the “electric potential energy per unit charge.” That is,

$$V = \frac{U_E}{q_0}$$

where V is measured in (Joules/Coulomb) and $1 \text{ (J/C)} \equiv 1 \text{ “Volt”}$
and depends only on the location in space.

Potential Difference


$$\Delta V = V_{final} - V_{initial} = (\Delta U_E / q_0) = (-W_{field} / q_0)$$

$$\Delta V = - \int_A^B \vec{E} \cdot d\vec{s}$$

Again, since the \mathbf{F}_{field} is conservative,

ΔV is path independent.

Example: Uniform \vec{E} -field




$$\Delta V = V_B - V_A = - \int_A^B \vec{E} \cdot d\vec{s} = -Ed$$

$$\Delta U = q_0 \Delta V = -q_0 Ed$$

If $q_0 > 0$, then $\Delta U < 0$ (particle moves to a lower U .)

Uniform \vec{E} -field (cont'd)



$$\begin{aligned}\Delta V &= V_C - V_A = - \int_A^C \vec{E} \cdot d\vec{s} = -E \cdot d' \\ &= -Ed' \cos\theta = -Ed\end{aligned}$$

For path $A \rightarrow B \rightarrow C$, $\Delta V = -Ed + \left(- \int_B^C \vec{E} \cdot d\vec{s} \right) = -Ed$
0, since $\vec{E} \perp d\vec{s}$ along path BC .


$\Delta V_{AC} = \Delta V_{AB}$ implies $V_C = V_B$.

Equipotential Contours/Surfaces

Paths along which the electric potential is constant are referred to as **equipotential contours**.

Question:

If \mathbf{E} points to the right,
is V higher or lower on
the left side?



Answer: V is higher on the left side.

Question

To move an electron from 90 V to 70 V does an external agent do positive work, negative work or zero work?

A) $W_{ext} > 0$

B) $W_{ext} < 0$

C) $W_{ext} = 0$

D) Not enough information.


Answer: $W_{ext} > 0$

Electric Potential from a Point Charge

$$\Delta V = V_B - V_A = - \int_A^B \vec{E} \cdot d\vec{s}, \text{ where } \vec{E} = \frac{kq}{r^2} \hat{r}.$$

$$\text{Then, } \Delta V = - \int_A^B \frac{kq}{r^2} \hat{r} \cdot d\vec{s}$$

where $\hat{r} \cdot d\vec{s} = d\text{scos}\theta = dr$ (the projection of $d\vec{s}$ along \hat{r}).



$$\Delta V = - \int_A^B \frac{kq}{r^2} dr = kq \left(\frac{1}{r_B} - \frac{1}{r_A} \right).$$

Letting $r_A = \infty$, then $V_A = 0$, and

$$V_B = \Delta V_B = \frac{kq}{r_B}$$

Some things to note:


- For a point charge, V at a location P in space depends only on radial the coordinate r from the charge.
- Electric potential superposition. So, for two or more points charges:

$$V_P = V_{1P} + V_{2P} + V_{3P} + \dots + V_{NP} = \sum_{i=1}^N V_{iP} = k \sum_{i=1}^N \frac{q_i}{r_i}$$

- V_P is an **algebraic sum** rather than a vector sum. Thus, it is generally easier to calculate V than to calculate \mathbf{E} .

Electric Potential Energy

Now bring a q_2 from ∞ and place it a distance r_{12} from q_1 :




$$U_E = q_2 V_1 = \frac{kq_1 q_2}{r_{12}} \text{ for the 2-particle system.}$$

If instead you bring q_1 from ∞ and place it a distance r_{12} from q_2 , then...

$$U_E = q_1 V_2 = \frac{kq_1 q_2}{r_{12}} \text{ (the same.)}$$

Now, what happens when you then bring in a third point charge and place it at P near the first two?



Then $\Delta U = U_f - U_i = q_3 V_P = q_3(V_1 + V_2)$

The total electrical potential energy of the 3-particle system is $U_f = U_i + \Delta U = U_i + q_3 V_1 + q_3 V_2$ or

$$U_f = \frac{kq_1q_2}{r_{12}} + \frac{kq_1q_3}{r_{13}} + \frac{kq_2q_3}{r_{23}}$$

To calculate the total U_E , you must sum over every pair of charges. **U_E does not obey superposition!**

Electric Potential from a Dipole

$$\text{At } P: V_P = \sum_{i=1}^2 V_i = V_+ + V_- = k \left(\frac{q}{r_+} + \frac{-q}{r_-} \right) = kq \left(\frac{r_- + r_+}{r_+ r_-} \right)$$

For $r \gg d$:

$$r_- + r_+ \approx d \cos \theta$$

$$\text{and } r_+ r_- \approx r^2.$$

$$\text{Thus, } V = kq \frac{d \cos \theta}{r^2} = k \frac{p \cos \theta}{r^2},$$

since $p = qd$.

Where $r_+ = r_-$ (as in the case of any point in the xz -plane),
 $V = 0$.

